

# Release Notes

## Firmware MTi-670 v1.1.2, MTi-7 v1.5.13

Author: Product Manager

Date: Oct, 2019



### 1 About this release

This document describes new **beta** firmware releases for the GNSS devices within the MTi 1-series, MTi-100 series and MTi 600-series devices.

### 2 Deliverables

Table 1: Deliverables

Product Family	Product types	Generation /HW version	FW version	Comments
MTi 1-series	MTi-1 (IMU) MTi-2 (VRU) MTi-3 (AHRS)	V2	-	
	MTi-7 (GNSS/INS)	V2	<b>1.5.13-beta</b>	
MTi 10-series	MTi-10 (IMU) MTi-20 (VRU) MTi-30 (AHRS)	5th generation	-	
MTi 100-series	MTi-100 (IMU) MTi-200 (VRU) MTi-300 (AHRS)	5th generation	-	
	MTi-G-710 (GNSS/INS)	5th generation	<b>1.11.12-beta</b>	
MTi 600-series	MTi-610 (IMU) MTi-620 (VRU) MTi-630 (AHRS)	V1	-	
	MTi-670 (GNSS/INS)		<b>1.1.2-beta</b>	

### 3 Tested with

Table 2: Overview of the tested + supported products

Product	Component	Version	Comments
<b>MT Software Suite</b>	MT Manager, MT SDK, Magnetic Field Mapper, MFM SDK ROS node	<b>2019.3.2-beta</b>	Released together with these beta firmwares
<b>Firmware Updater</b>		4.2.7	Latest stable version, downloadable from the Xsens website

# Release Notes

## Firmware MTi-670 v1.1.2, MTi-7 v1.5.13

Author: Product Manager

Date: Oct, 2019



## 4 Bug fixes, improvements and features

This section details the list of issues that are contained in this release.

**Table 3: Firmware**

<b>Improvements &amp; features</b>		
Feature	MTi600-77 MTONE-313	Added support to MTi-670 and MTi-7 for the uBlox ZED family GNSS receivers
Feature	MTi600-79	Added support to MTi-670 and MTi-7 for the uBlox NEO family GNSS receivers
Feature	MTi600-99	Added orientation smoother for MTi-670
Improvement	MTi600-157	MTi-670 now supports output of GNSS satellite info
Improvement	MKVFW-80	Updated WMM model to 2015v2 for MTi 100-series
Feature	MKVFW-84	MTi-G-710 can now initialize to a user-specified heading value
Improvement	MTONE-318	Updated WMM model to 2015v2 for MTi 1-series

## 5 Current product overview

This section lists all the products and their current stable and beta versions.

**Table 4: Complete list of products and their current versions**

<b>Deliverable</b>	<b>Product(s)</b>	<b>HW version</b>	<b>Current <i>stable</i> version</b>	<b>Current <i>beta</i> version</b>	<b>Comments</b>
Firmware	MTi-1 MTi-2 MTi-3	V2	1.4.0	1.5.2	
	MTi-7	V2	1.4.0	<b>1.5.13</b>	
	MTi-10 MTi-20 MTi-30	5 <sup>th</sup> generation	1.10.0	1.11.2	
	MTi-100 MTi-200 MTi-300	5 <sup>th</sup> generation	1.10.0	1.11.2	
	MTi-G-710	5 <sup>th</sup> generation	1.10.0	<b>1.11.12</b>	
	MTi 610 MTi 620 MTi 630	V1	1.0.0	-	
	MTi 670	V1	1.0.0	<b>1.1.2</b>	
Firmware Updater	for all Xsens devices		4.2.7	-	
MT Software Suite	MT Manager  MT SDK (incl. ROS node driver) Magnetic Field Mapper MFM SDK		2019.2	<b>2019.3.2</b>	