

Xsens DOT

Firmware Changelogs

Author: Product Manager
Last updated: April 24, 2020
Document: XD0207P



Symbol	Meaning
+	Added
^	Changed
!	Note
#	Fixed
-	Removed

Version 1.3.0

Release date: April 24, 2020

Release type: Beta

Compatible APK and SDK versions: 2020.0, 2020.1

- ^ Introducing 12 new measurement modes with support to different measurement quantities to reduce payload demands on BLE transmission.
- ^ The device's Bluetooth transmit power has been increased.
- ^ The transmit buffering has been increased to cope with any transient data loss.
- + Euler angles, delta_q, delta_v, angular velocity and acceleration data quantities have been added to the data output options.
- + Heading reset feature support.
- + Support for saving firmware crash logs has been added.
- + Xsens Bluetooth company ID.
- Support to FW v1.0.0 'Default' measurement mode has been removed.
- # Firmware crash associated with a packet counter reset has been fixed.
- # Fixed the issue where OTA could not be started after heat protection kicked in.
- # Reset issue of sensor fusion filter upon starting measurement has been fixed.