

Symbol	Meaning
+	Added
^	Changed
!	Note
#	Fixed
-	Removed

### Version 2020.2

**Release date: August 24, 2020**

**Release type: Stable**

**Compatible firmware versions: 1.0.0, 1.4.0**

- + Added heading reset function.
- + Support all the payload modes in real-time streaming.
- + Added crash information collection.
- + Support recording function.
- + Support synchronization function.
- + Added serial number support.
- ^ Changed all the big endianness settings to little endianness.
- ^ Reduced the data loss rate in real-time streaming.
- ^ Change "dQ", "dV" to "dq", "dv".
- Remove OTA and MFM functions.
- Remove support for special characters in tag name.
- # Fixed the wrong packet counter in logging csv after sensor reset.
- # Fixed the NaN values in logging csv of 3 modes in real-time streaming.
- # Fixed the reconnection malfunction issue.
- # Fixed the incorrect status bytes in 3 measurement mode.